

Running an HLC

Prerequisite is that the [Experiment is set up](#).

Start HLC from the LCC

1. On the right, go to the [Setup](#) tab
2. In the script path, select the desired HLC.
3. Click *Deploy*.
4. On the right, go to the [Timer](#) tab
5. Wait for the timer with the ID *middleware* to show up.
6. Click *Start*.
7. Let your experiment run as desired.
8. Click *Stop* and *Reset* in the [Timer](#) tab.
9. On the right, go to the [Setup](#) tab
10. Click *Kill* in the [Setup](#) tab.

Start HLC externally

There are multiple reasons you might want to run an HLC from outside the LCC, e.g., for easier debugging.

Repeat the steps as above, but in step 3, you leave the HLC path blank and [run your HLC externally](#) (e.g. in MATLAB or in a terminal for a C++ script).